IND8002 UHF RFID Reader serial Interface protocol

V2.38



| 1 SPECIFICATION OF THE DATA PACKET | 3 |
|--|----|
| 1. 1 RS-232 CONFIGURATIONS | 3 |
| 1. 2 DATA PACKET DEFINITION | |
| 1. 2. 1 HOST COMMAND DATA PACKET DEFINITION | 3 |
| 1. 2. 2 RESPONSE PACKET DEFINITION | 3 |
| 2 COMMAND DEFINITION | 4 |
| 2. 1 READER CONTROL COMMANDS | 6 |
| 2.1.1 CMD_RESET | 6 |
| 2.1.2 CMD_SET_UART_BAUDRATE | 6 |
| 2.1.3 CMD_GET_FIRMWARE_VERSION | 7 |
| 2.1.4 CMD_SET_READER_ADDRESS | 8 |
| 2.1.5 CMD_SET_WORK_ANTENNA | 9 |
| 2.1.6 CMD_GET_WORK_ANTENNA | 10 |
| 2.1.7 CMD_SET_OUTPUT_POWER | 11 |
| 2.1.8 CMD_GET_OUTPUT_POWER | 12 |
| 2.1.9 CMD_SET_FREQUENCY_REGION | 13 |
| 2.1.10 cmd_get_frequency_region | 15 |
| 2.1.11 CMD_SET_BEEPER_MODE | 16 |
| 2.1.12 CMD_GET_READER_TEMPERATURE | 17 |
| 2.1.13 CMD_READ_GPIO_VALUE | 18 |
| 2.1.14 CMD_WRITE_GPIO_VALUE | 18 |
| 2.1.15 CMD_SET_ANT_CONNECTION_DETECTOR | 19 |
| 2.1.16 CMD_GET_ANT_CONNECTION_DETECTOR | 20 |
| 2.1.17 CMD_SET_TEMPORARY_OUTPUT_POWER | 21 |
| 2.1.18 CMD_SET_READER_IDENTIFIER | 22 |
| 2.1.19 CMD_GET_READER_IDENTIFIER | 23 |
| 2.1.20 CMD_SET_RF_LINK_PROFILE | 24 |
| 2.1.21 CMD_GET_RF_LINK_PROFILE | 25 |
| 2.1.22 CMD_GET_RF_PORT_RETURN_LOSS | 26 |
| 2. 2 18000-6C COMMANDS | 27 |
| 2.2.1 CMD_INVENTORY | 27 |
| 2.2.2 CMD_READ | 28 |
| 2.2.3 CMD_WRITE | 29 |
| 2.2.4 CMD_LOCK | 30 |
| 2.2.5 CMD_KILL | 31 |
| 2.2.6 CMD_SET_ACCESS_EPC_MATCH | 32 |
| 2.2.7 CMD_GET_ACCESS_EPC_MATCH | 32 |
| 2.2.8 cmd_real_time_inventory | 33 |
| 2.2.9 CMD_FAST_SWITCH_ANT_INVENTORY | 35 |
| 2.2.10 cmd_customized_session_target_inventory | 37 |
| 2.2.11 CMD_SET_IMPINJ_FAST_TID | 39 |

YR8001 UHF RFID Serial Interface Protocol User's Guide V 2.38

| 2.2.12 CMD_SET_AND_SAVE_IMPINJ_FAST_TID | 40 |
|---|----|
| 2.2.13 CMD_GET_IMPINJ_FAST_TID | 40 |
| 2.3 ISO 18000-6B COMMANDS | 41 |
| 2.3.1 CMD_ISO18000_6B_INVENTORY | 41 |
| 2.3.2 CMD_ISO18000_6B_READ | 42 |
| 2.3.3 CMD_ISO18000_6B_WRITE | 43 |
| 2.3.4 CMD_ISO18000_6B_LOCK | 44 |
| 2.3.5 CMD_ISO18000_6B_QUERY_LOCK | 45 |
| 2. 4 BUFFER OPERATION COMMANDS | 46 |
| 2.4.1 CMD_GET_INVENTORY_BUFFER | 46 |
| 2.4.2 CMD_GET_AND_RESET_INVENTORY_BUFFER | 47 |
| 2.4.3 CMD_GET_INVENTORY_BUFFER_TAG_COUNT | 47 |
| 2.4.4 CMD_RESET_INVENTORY_BUFFER | 47 |
| 3 ERROR CODE | 48 |
| 4 FREQUENCY PARAMETER REFERENCE TABLE | 50 |
| 5 RSSI PARAMETER REFERENCE TABLE | 51 |
| 6 CHECKSUM FUNCTION (STANDARD C LANGUAGE) | 52 |

1 Specification of the Data Packet

This protocol is a communication specification for controlling the UHF RFID reader by its host computer via serial interface.

Commands and responses consist of byte streams. The lengths of the streams are variable, and the packets are checked by checksum.

1.1 RS-232 Configurations

The physical interface is compatible with the RS - 232 specifications.

1start bit, 8 data bits, 1 stop bit, no even odd check..

The baud rate can be set to 38400bps or 115200bps. The default baud rate is 115200bps.

1.2 Data Packet Definition

1.2.1 Host Command Data Packet Definition

| Head | Len | Address | Cmd | Data | Check | | |
|---------|---------|---------|---|--|-----------------------------------|--|--|
| 0xA0 | 1 Byte | 1 Byte | 1 Byte | N Bytes | 1 Byte | | |
| | | | | | | | |
| | | Н | lead | Head of the packet | t, every packet starts with 0xA0. | | |
| | | I | Len | Length of the page | eket bytes. Starts from the third | | |
| | | | | byte, the Head, Len bytes are exclusive. | | | |
| Address | | dress | Reader's address for RS-485 connection. The | | | | |
| Parar | meter | | | common addresses are $0\sim254(0xFE)$, 255 (0xFF) | | | |
| Descr | ription | | | is the public address. The reader accepts the | | | |
| | | | | address of itself ar | d the public address. | | |
| Cmd | | | md | Command byte. | | | |
| Data | | | D ata | Command parameters. | | | |
| | | Cl | heck | Checksum. Check | all the bytes except itself. | | |

1.2.2 Response Packet Definition

| Head | Len | Address | Data | Check | | |
|--|----------|---------|---|--------------------------------|--|--|
| 0xA0 | 1 Byte | 1 Byte | N Bytes | 1 Byte | | |
| | | | | | | |
| | | Head | Head of the packet, | every packet starts with 0xA0. | | |
| | | Len | Length of the packet bytes. Starts from the third | | | |
| Para | ameter | | byte, the Head, Len bytes are exclusive. | | | |
| Desc | cription | Address | Reader's address. | | | |
| Data Data from the reader. | | | | · . | | |
| Check Checksum. Check all the bytes except itself. | | | | | | |

2 Command Definition

Comprehensive Command Table

| ID | Code | Name | Description |
|------|----------|---------------------------------|---|
| Read | ler Cont | rol Commands | |
| 1 | 0x70 | cmd_reset | Reset reader. |
| 2 | 0x71 | cmd_set_uart_baudrate | Set baud rate of serial port. |
| 3 | 0x72 | cmd_get_firmware_version | Get firmware version. |
| 4 | 0x73 | cmd_set_reader_address | Set reader's address. |
| 5 | 0x74 | cmd_set_work_antenna | Set working antenna. |
| 6 | 0x75 | cmd_get_work_antenna | Query current working antenna. |
| 7 | 0x76 | cmd_set_output_power | Set RF output power. |
| 8 | 0x77 | cmd_get_output_power | Query current RF output power. |
| 9 | 0x78 | cmd_set_frequency_region | Set RF frequency spectrum. |
| 10 | 0x79 | cmd_get_frequency_region | Query RF frequency spectrum. |
| 11 | 0x7A | cmd_set_beeper_mode | Set reader's buzzer hehavior. |
| 12 | 0x7B | cmd_get_reader_temperature | Check reader's internal temperature. |
| 13 | 0x60 | cmd_read_gpio_value | Get GPIO1, GPIO2 status. |
| 14 | 0x61 | cmd_write_gpio_value | Set GPIO3, GPIO4 status. |
| 15 | 0x62 | cmd_set_ant_connection_detector | Set antenna detector status. |
| 16 | 0x63 | cmd_get_ant_connection_detector | Get antenna detector status. |
| 17 | 0x66 | cmd_set_temporary_output_power | Set RF power without saving to flash. |
| 18 | 0x67 | cmd_set_reader_identifier | Set reader's identification bytes. |
| 19 | 0x68 | cmd_get_reader_identifier | Get reader's identification bytes. |
| 20 | 0x69 | cmd_set_rf_link_profile | Set RF link profile. |
| 21 | 0x6A | cmd_get_rf_link_profile | Get RF link profile. |
| 22 | 0x7E | cmd_get_rf_port_return_loss | Get current antenna port's return loss. |
| 1800 | 0-6C Co | mmands | |
| 23 | 0x80 | cmd_inventory | Inventory EPC C1G2 tags to buffer. |

YR8001 UHF RFID Serial Interface Protocol User's Guide V 2.38

| 24 | 0x81 | cmd_read | Read EPC C1G2 tag(s). | |
|-------|-----------|---|--|--|
| 25 | 0x82 | cmd_write | Write EPC C1G2 tag(s). | |
| 26 | 0x83 | cmd_lock | Lock EPC C1G2 tag(s). | |
| 27 | 0x84 | cmd_kill | Kill EPC C1G2 tag(s). | |
| 28 | 0x85 | cmd_set_access_epc_match | Set tag access filter by EPC. | |
| 29 | 0x86 | cmd_get_access_epc_match | Query access filter by EPC. | |
| 30 | 0x89 | cmd_real_time_inventory | Inventory tags in real time mode. | |
| 31 | 0x8A | cmd_fast_switch_ant_inventory | Real time inventory with fast ant switch. | |
| 32 | 0x8B | cmd_customized_session_target_inventory | Inventory with desired session and inventoried | |
| | | | flag. | |
| 33 | 0x8C | cmd_set_impinj_fast_tid | Set impinj FastTID function. | |
| | | | (Without saving to FLASH) | |
| 34 | 0x8D | cmd_set_and_save_impinj_fast_tid | Set impinj FastTID function. | |
| | | | (Save to FLASH) | |
| 35 | 0x8E | cmd_get_impinj_fast_tid | Get current FastTID setting. | |
| ISO1 | 8000-6E | 3 Commands | | |
| 36 | 0xB0 | cmd_iso18000_6b_inventory | Inventory 18000-6B tag(s). | |
| 37 | 0xB1 | cmd_iso18000_6b_read | Read 18000-6B tag. | |
| 38 | 0xB2 | cmd_iso18000_6b_write | Write 18000-6B tag. | |
| 39 | 0xB3 | cmd_iso18000_6b_lock | Lock 18000-6B tag data byte. | |
| 40 | 0xB4 | cmd_iso18000_6b_query_lock | Query lock 18000-6B tag data byte. | |
| Buffe | er contro | ol Commands | | |
| 41 | 0x90 | cmd_get_inventory_buffer | Get and clear buffered data. | |
| 42 | 0x91 | cmd_get_and_reset_inventory_buffer | Get buffered data without clearing. | |
| 43 | 0x92 | cmd_get_inventory_buffer_tag_count | Query how many tags are buffered. | |
| 44 | 0x93 | cmd_reset_inventory_buffer | Clear buffer. | |
| | | I . | 1 | |

2.1 Reader Control Commands

2.1.1 cmd_reset

Host packet:

| Head | Len | Address | Cmd | Check |
|------|------|---------|------|-------|
| 0xA0 | 0x03 | | 0x70 | |

◆Succeeded: No data response, reader resets and restarts. Buzzer beeps.

♦Failed:

Response packet:

| Head | Len | Address | Cmd | ErrorCode | Check |
|-----------------------|-----------|-------------|------|-----------|-------|
| 0xA0 | 0x04 | | 0x70 | | |
| | | | | | |
| Parameter Description | ErrorCode | Error code. | | | |

2.1.2 cmd_set_uart_baudrate

Host packet:

| Head | Len | Address | Cmd | BaudRate | Check |
|-------------|----------|---------|------|-------------|-------|
| 0xA0 | 0x04 | | 0x71 | | |
| | | | | | |
| Parameter | DaydData | 0x03 | | 38400 bps. | |
| Description | BaudRate | 0x04 | | 115200 bps. | |

♦Succeeded:

Response packet:

| Head | Len | Address | Cmd | ErrorCode | Check |
|------|------|---------|------|----------------|-------|
| 0xA0 | 0x04 | | 0x71 | CommandSuccess | |

When reader gets this command right, it responses with previous baud rate, then reader resets. The new baud rate parameter is preserved in the internal flash, won't be lost when power off.

♦Failed:

Response packet:

| Head | Len | Address | Cmd | ErrorCode | Check |
|-----------------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0x71 | | |
| | | | | | |
| Parameter Description | ErrorCode | | Err | or code. | |

2.1.3 cmd_get_firmware_version

Host packet:

| Head | Len | Address | Cmd | Check |
|------|------|---------|------|-------|
| 0xA0 | 0x03 | | 0x72 | |

| Head | Len | Address | Cmd | Major | Minor | Check | | |
|-------------|-------|-----------------------------|-----------------------------|-------|-------|-------|--|--|
| 0xA0 | 0x05 | | 0x72 | | | | | |
| | | | | | | | | |
| Parameter | Major | | The major firmware version. | | | | | |
| Description | Minor | The minor firmware version. | | | | | | |

2.1.4 cmd_set_reader_address

Host packet:

| Head | Len | Address | Cmd | Address | Check |
|-------------|-------------|---------|---------------|---------------------|-------|
| 0xA0 | 0x04 | | 0x73 | | |
| | | | | | |
| Parameter | ۸ ما ماسم م | n | ٠ | ass from 0 to 254 | |
| Description | Address | K | teader's addr | ess, from 0 to 254. | |

♦Succeeded:

Response packet:

| Head | Len | Address | Cmd | ErrorCode | Check |
|------|------|---------|------|----------------|-------|
| 0xA0 | 0x04 | | 0x73 | CommandSuccess | |

The new reader address takes effect immediately, and preserved in the internal flash, won't be lost when power off.

♦Failed:

| Head | Len | Address | Cmd | ErrorCode | Check |
|-------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0x73 | | |
| | | | | | |
| Parameter | E C. 1. | | Г | 1 . | |
| Description | ErrorCode | | Eri | or code. | |

2.1.5 cmd_set_work_antenna

Host packet:

| Head | Len | Address | Cmd | AntennaID | Check |
|-------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0x74 | | |
| | | | | | |
| | | | 0x00 | Antenna | ı 1. |
| Parameter | AntennaID | Working | 0x01 | Antenna | ı 2. |
| Description | Antennaid | Antenna | 0x02 | Antenna | ı 3. |
| | | | 0x03 | Antenna | ւ 4. |

♦Succeeded:

Response packet:

| Head | Len | Address | Cmd | ErrorCode | Check |
|------|------|---------|------|----------------|-------|
| 0xA0 | 0x04 | | 0x74 | CommandSuccess | |

♦Failed:

| Head | Len | Address | Cmd | ErrorCode | Check |
|-------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0x74 | | |
| | | | | | |
| Parameter | Г С 1 | | Г | 1 | |
| Description | ErrorCode | | En | ror code. | |

2.1.6 cmd_get_work_antenna

Host packet:

| Head | Len | Address | Cmd | Check |
|------|------|---------|------|-------|
| 0xA0 | 0x03 | | 0x75 | |

| Head | Len | Address | Cmd | AntennaID | Check | | | | |
|-------------|---|---------|------|------------|-------|--|--|--|--|
| 0xA0 | 0x04 | | 0x75 | | | | | | |
| | | | | | | | | | |
| | A . | ID | 0x00 | Antenna | ı 1. | | | | |
| Parameter | AntennaID (Current Working Antenna) | | 0x01 | Antenna | ı 2. | | | | |
| Description | | | 0x02 | Antenna 3. | | | | | |
| | Ante | illa j | 0x03 | Antenna 4. | | | | | |

2.1.7 cmd_set_output_power

Host packet:

| Head | Len | Address | Cmd | RfPower | Check | | | |
|-------------|----------|--|------|--------------|-------|--|--|--|
| 0xA0 | 0x04 | | 0x76 | | | | | |
| | | | | | | | | |
| Parameter | DfDayyan | RF output power, range from 0 to $33(0x00 - 0x21)$, the | | | | | | |
| Description | RfPower | | | unit is dBm. | | | | |

Or:

| Head | Len | Address | Cmd | Power1 | Power2 | Power3 | Power4 | Check | |
|--------------|--------|----------|---|-----------------|---------------|-----------------|----------------|-------|--|
| 0xA0 | 0x07 | | 0x76 | | | | | | |
| | | | | | | | | | |
| | Power1 | Output p | Output power of antenna 1, range from 0 to $33(0x00 - 0x21)$, the unit is dBm. | | | | | | |
| 全粉 沿明 | Power2 | Output p | ower of ar | ntenna 2, range | from 0 to 33(| 0x00 - 0x21), t | he unit is dBn | n. | |
| 参数说明 | Power3 | Output p | Output power of antenna 3, range from 0 to $33(0x00 - 0x21)$, the unit is dBm. | | | | | | |
| | Power4 | Output p | ower of ar | ntenna 4, range | from 0 to 33(| 0x00 - 0x21), t | he unit is dBn | n. | |

♦Succeeded:

Response packet:

| Head | Len | Address | Cmd | ErrorCode | Check |
|------|------|---------|------|----------------|-------|
| 0xA0 | 0x04 | | 0x76 | CommandSuccess | |

♦Failed:

Response packet:

| Head | Len | Address | Cmd | ErrorCode | Check |
|-----------------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0x76 | | |
| | | | | | |
| Parameter Description | ErrorCode | | Err | or code. | |

The output power value will be saved to the internal flash so that it won't be lost after power off.

Attention:

- **★**This command consumes more than 100mS.
- ★ If you want you change the output power frequently, please use Cmd_set_temporary_output_power command, which doesn't reduce the life of the internal flash memory.

2.1.8 cmd_get_output_power

Host packet:

| Head | Len | Address | Cmd | Check |
|------|------|---------|------|-------|
| 0xA0 | 0x03 | | 0x77 | |

If all antennas have the same output power value, then

Response packet:

| Head | Len | Address | Cmd | OutputPower | Check | | | |
|-------------|-------------|------------------------------------|------|-------------|-------|--|--|--|
| 0xA0 | 0x04 | | 0x77 | | | | | |
| | | | | | | | | |
| Parameter | O44D | tputPower Current RF output power. | | | | | | |
| Description | OutputPower | | | | | | | |

Otherwise response packet is:

| Head | Len | Address | Cmd | Power1 | Power2 | Power3 | Power4 | Check | | | |
|-------|--------|-----------|--|-----------------|---------------|------------------|----------------|-------|--|--|--|
| 0xA0 | 0x07 | | 0x77 | | | | | | | | |
| | | | | | | | | | | | |
| | Power1 | Output po | Output power of antenna 1, range from 0 to 33(0x00 – 0x21), the unit is dBm. | | | | | | | | |
| 参数说明 | Power2 | Output po | ower of ar | ntenna 2, range | from 0 to 33(| 0x00 - 0x21), to | he unit is dBn | n. | | | |
| 一 多 级 | Power3 | Output pe | Output power of antenna 3, range from 0 to 33(0x00 – 0x21), the unit is dBm. | | | | | | | | |
| | Power4 | Output po | ower of ar | ntenna 4, range | from 0 to 33(| 0x00 - 0x21), to | he unit is dBn | n. | | | |

2.1.9 cmd_set_frequency_region

There are two methods to define the RF spectrum.

Method A: Use system default frequencies (Please see frequency parameter reference table).

Host packet:

| Head | Len | Address | Cmd | Regio | on Sta | artFreq | EndFreq | Check |
|-------------|------------|-----------|------|-------|---------------------------|------------|---------------|--------------|
| 0xA0 | 0x06 | | 0x78 | | | | | |
| | | | | | | | | |
| | | Spectrum | 0x0 |)1 | | | FCC | |
| Region | regulation | 0x0 |)2 | | | ETSI | | |
| | regulation | 0x0 |)3 | | | CHN | | |
| | StartFreq | Start | | | Setup | the rang | ge of the | RF output |
| Parameter | | frequency | | | spectrum. | | | |
| | | of the | | | The rules are: | | | |
| Description | | spectrum | | | 1,Start | frequenc | ey and end | l frequency |
| Description | | End | | | | | range of the | he specified |
| | | frequency | | | regulati | | | |
| | EndFreq | of the | | | | • | • | e equal or |
| | | spectrum | | | lower than end frequency. | | | |
| | | F | | | 3, End | frequency | y equals star | rt frequency |
| | | | | | means u | use single | frequency p | ooint. |

Method B: Use user defined frequencies.

Host packet:

| Head | Len | Address | Cmd | Region | FreqSpace | RreqQuantity | StartFreq | Check | |
|------|--------------|-----------------------|--|--------|-------------------|---|-----------|-------|--|
| 0xA0 | 0x09 | | 0x78 | 0x04 | | | 3bytes | | |
| | | | | | | | | | |
| | Region | Spectrum regulation | This byte is fixed to 0x04. | | | | | | |
| | FreqSpace | Frequency space | Frequency space = FreqSpace x 10KHz. | | | | | | |
| 参数说明 | FreqQuantity | Frequency Quantity | - | • | the single carrie | quency, if set this ber frequency. This than 0. | • | | |
| | StartFreq | Start Frequency | The unit is KHz. Set the start frequency with hex format, for example, 915000KHz = 0D F6 38 KHz. | | | | | | |

♦Succeeded:

Response packet:

| Head | Len | Address | Cmd | ErrorCode | Check |
|------|------|---------|------|----------------|-------|
| 0xA0 | 0x04 | | 0x78 | CommandSuccess | |

♦Failed:

| Head | Len | Address | Cmd | ErrorCode | Check | | | |
|-------------|-----------|------------------|------|-----------|-------|--|--|--|
| 0xA0 | 0x04 | | 0x78 | | | | | |
| | | | | | | | | |
| Parameter | ErrorCode | Code Error code. | | | | | | |
| Description | LiforCode | | 1511 | or code. | | | | |

2.1.10 cmd_get_frequency_region

Host packet:

| Head | Len | Address | Cmd | Check |
|------|------|---------|------|-------|
| 0xA0 | 0x03 | | 0x79 | |

If system frequencies are used, the response packet is:

| Head | Len | Address | Cmd | Regio | n StartFreq | EndFreq | Check | |
|-------------|-----------------------------------|------------|------|-------|----------------------------------|---------|-------|--|
| 0xA0 | 0x06 | | 0x79 | | | | | |
| | | | | | | | | |
| | | G 4 | 0x0 |)1 | FCC. | | | |
| | Region | Spectrum | 0x02 | | ETSI. | | | |
| Danamatan | | regulation | 0x03 | | CHN. | | | |
| Description | arameter StartFreq StartFreq free | | | | Start frequency of the spectrum. | | | |
| | EndFreq | End | | | F 16 64 | | | |
| | | frequency | | | End frequency of the spectrum. | | | |

If user defined frequencies are used, the response packet is:

| | if user defined frequencies are used, the response packet is. | | | | | | | | | | |
|------|---|------------|--|--------------|-------------------|-----------------------|------------------|-------------|--|--|--|
| Head | Len | Address | Cmd | Region | FreqSpace | RreqQuantity | StartFreq | Check | | | |
| 0xA0 | 0x09 | | 0x79 | 0x04 | | | 3bytes | | | | |
| | | | | | | | | | | | |
| | Region | Spectrum | This byte is fixed to 0x04. | | | | | | | | |
| | | regulation | | | | | | | | | |
| | FreqSpace | Frequency | | E, | raguancy choca | = FreqSpace x 10k | /Ц ₇ | | | | |
| 参数说明 | | space | | 11 | requeries space | - Freqspace x for | XIIZ. | | | | |
| 多奴见明 | FreqQuantity | Frequency | This quan | tity includ | es the start freq | uency, if set this by | te to 1, means | s use start | | | |
| | | Quantity | freq | uency as the | he single freque | ency. This byte sho | uldn't be set to | o 0. | | | |
| | StartFreq | Start | The unit is KHz. Get the start frequency with hex format, for example, | | | | | | | | |
| | | Frequency | | | 915000KHz | z = 0D F6 38 KHz. | | | | | |

2.1.11 cmd_set_beeper_mode

Host packet:

| Head | Len | Address | Cmd | Mode | Check | |
|-------------|---------|---------------------------|------|-----------------------------|-----------|--|
| 0xA0 | 0x04 | | 0x7A | | | |
| | | | | | | |
| | | | 0x00 | Quiet. | | |
| Parameter | | | 0x01 | Beep after every | inventory | |
| Description | N | Mode (Buzzer behavior) | | round if tag(s) identified. | | |
| Description | (Buzzei | | | Beep after every tag has | | |
| | | | | identified. | | |

♦Succeeded:

Response packet:

| Head | Len | Address | Cmd | ErrorCode | Check |
|------|------|---------|------|----------------|-------|
| 0xA0 | 0x04 | | 0x7A | CommandSuccess | |

If this command succeeded, the value will be stared in the internal flash, won't be lost when power off.

Attention:

★Buzzer behavior 0x02(Beep after every tag has identified) occupies CPU process time that affects anti-collision algorithm significantly. It is recommended that this option should be used for tag test.

♦Failed:

| Head | Len | Address | Cmd | ErrorCode | Check |
|-----------------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0x7A | | |
| | | | | | |
| Parameter Description | ErrorCode | | Er | ror code. | |

2.1.12 cmd_get_reader_temperature

Host packet:

| Head | Len | Address | Cmd | Check |
|------|------|---------|------|-------|
| 0xA0 | 0x03 | | 0x7B | |
| | | | | |

♦Succeeded:

Response packet:

| Head | Len | Address | Cmd | PlusMinus | Temp | Check |
|-------------|-----------|---------|---------|-----------|---------|-------|
| 0xA0 | 0x05 | | 0x7B | | | |
| | | | | | | |
| D | PlusMinus | | 0x | 00 | Plus. | |
| Parameter | | | 0x01 | | Minus. | |
| Description | Te | mp | Celsius | | legree. | |

♦Failed:

| Head | Len | Address | Cmd | ErrorCode | Check |
|-----------------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0x7B | | |
| | | | | | |
| Parameter Description | ErrorCode | | Err | or code. | |

2.1.13 cmd_read_gpio_value

Host packet:

| Head | Len | Address | Cmd | Check |
|------|------|---------|------|-------|
| 0xA0 | 0x03 | | 0x60 | |

Response packet:

| Head | Len | Address | Cmd | Gpio_1 | Gpio_2 | Check | | |
|-----------------------|------|---------|------|--------------------|------------|-------|--|--|
| 0xA0 | 0x05 | | 0x60 | | | | | |
| | | | | | | | | |
| | | | 0x00 | | Gpio1 is | low. | | |
| Domonton Dos | | Gpio_1 | 0x01 | | Gpio1 is l | nigh. | | |
| Parameter Description | | Carta 2 | 0x00 | 0x00 Gpio2 is low. | | low. | | |
| | | Gpio_2 | 0x01 | | Gpio2 is l | nigh. | | |

2.1.14 cmd_write_gpio_value

Host packet:

| Head | Len | Address | Cmd | ChooseGpio | | GpioValue | Check | |
|-------------|------|------------|------|------------|--|-----------------|-------|--|
| 0xA0 | 0x05 | | 0x61 | | | | | |
| | | | | | | | | |
| | | Chanach | 0x03 | | | Set GPIO 3 | | |
| Paramete | er | ChooseGpio | 0x04 | | | Set GPIO 4 | | |
| Description | on | CricVelue | 0x00 | | | Set to low lev | el. | |
| | | GpioValue | 0x01 | | | Set to high lev | vel. | |

| Head | Len | Address | Cmd | ErrorCode | Check | | | |
|-------------|-----------|-------------|------|-----------|-------|--|--|--|
| 0xA0 | 0x04 | | 0x61 | | | | | |
| | | | | | | | | |
| Parameter | ErrorCode | Error code. | | | | | | |
| Description | ErrorCode | | ЕП | or code. | | | | |

2.1.15 cmd_set_ant_connection_detector

Host packet:

| Head | Len | Address | Cmd | DetectorSensitivity | Check |
|-----------------|---------|---------------------|------|------------------------------------|---------------|
| 0xA0 | 0x04 | | 0x62 | | |
| | | | | | |
| | | | 0x00 | Close connection d | etector. |
| | | | | Set the sensitivity of the antenna | |
| | | | | detector, the value is the | e return loss |
| Parameter Descr | ription | DetectorSensitivity | | of the antenna port. The | unit is dB. |
| | | | | The impedance match r | equirement |
| | | | | is more stringent when | this value |
| | | | | gets bigger. | |

| Head | Len | Address | Cmd | ErrorCode | Check |
|-----------------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0x62 | | |
| | | | | | |
| Parameter Description | ErrorCode | | Err | or code. | |

2.1.16 cmd_get_ant_connection_detector

Host packet:

| Head | Len | Address | Cmd | Check |
|------|------|---------|------|-------|
| 0xA0 | 0x03 | | 0x63 | |

| Head | Len | Address | Cmd | DetectorSensitivity | Check | |
|-----------------------|------------|---------------------|--|---|---------------|--|
| 0xA0 | 0x04 | | 0x63 | | | |
| | | | | | | |
| Parameter Description | | | 0x00 | Connection detector is closed. | | |
| | D-44 | | The sensitivity of the antenna detector, | | | |
| Parameter L | escription | DetectorSensitivity | | The sensitivity of the antenna dete the value is the return loss of the | n loss of the | |
| | | | | antenna port. The t | ınit is dB. | |

2.1.17 cmd_set_temporary_output_power

Host packet:

| Head | Len | Address | Cmd | RfPower | Check | | |
|-------------|---------|-------------|-------------|------------------|-----------------------|--|--|
| 0xA0 | 0x04 | | 0x66 | | | | |
| | | | | | | | |
| Parameter | D.fD | RF output p | power, rang | ge from 20-33(0: | x14 - 0x21), the unit | | |
| Description | RfPower | is dBm. | | | | | |

♦Succeeded:

Response packet:

| Head | Len | Address | Cmd | ErrorCode | Check |
|------|------|---------|------|----------------|-------|
| 0xA0 | 0x04 | | 0x66 | CommandSuccess | |

♦Failed:

Response packet:

| Head | Len | Address | Cmd | ErrorCode | Check |
|-----------------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0x66 | | |
| | | | | | |
| Parameter Description | ErrorCode | | Err | or code. | |

The output power value will **Not** be saved to the internal flash memory so that the output power will be restored from the internal flash memory after restart or power off.

Attention:

- **★**This command consumes less than 10uS.
- ★ If you want you change the output power frequently, please use this command, which doesn't reduce the life of the internal flash memory.

2.1.18 cmd_set_reader_identifier

Host packet:

| Head | Len | Address | Cmd | Identifier | Check | | | | |
|-------------|------------|---------|-----------------------|-------------------------|-------|--|--|--|--|
| 0xA0 | 0x0F | | 0x67 | 12 Bytes | | | | | |
| | | | | | | | | | |
| Parameter | T.14:£ | | D 1 2 11 ('C (121 () | | | | | | |
| Description | Identifier | | Reader s | s identifier (12 bytes) |). | | | | |

♦Succeeded:

Response packet::

| Head | Len | Address | Cmd | ErrorCode | Check |
|------|------|---------|------|----------------|-------|
| 0xA0 | 0x04 | | 0x67 | CommandSuccess | |

♦Failed:

Response packet:

| Head | Len | Address | Cmd | ErrorCode | Check |
|-----------------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0x67 | | |
| | | | | | |
| Parameter Description | ErrorCode | | Err | or code. | |

The identifier is stored in internal flash.

2.1.19 cmd_get_reader_identifier

Host packet:

| Head | Len | Address | Cmd | Check |
|------|------|---------|------|-------|
| 0xA0 | 0x03 | | 0x68 | |

♦Succeeded:

| Head | Len | Address | Cmd | Identifier | Check |
|-----------------------|------------|---------|----------|------------------|--------|
| 0xA0 | 0x0F | | 0x68 | 12 Bytes | |
| | | | | | |
| Parameter Description | Identifier | | Reader's | identifier (12 b | ytes). |

2.1.20 cmd_set_rf_link_profile

Host packet:

| Head | Len | Address | Cmd | ProfileID | Check | | |
|-------------|-----------|----------------|---|---------------------------------|-------|--|--|
| 0xA0 | 0x04 | | 0x69 | | | | |
| | | | | | | | |
| | ProfileID | 0xD0 | Pr | Profile 0: Tari 25uS,FM0 40KHz. | | | |
| D (| | 0D1 | Profile 1: Tari 25uS, Miller 4 250KHz. | | | | |
| Parameter | | ProfileID 0xD1 | Profile 1 is the recommended and default setting. | | | | |
| Description | | 0xD2 | Profile 2: Tari 25uS,Miller 4 300KHz. | | | | |
| | | 0xdD3 | Profile 3: Tari 6.25uS,FM0 400KHz. | | | | |

♦Succeeded:

Response packet:

| Head | Len | Address | Cmd | ErrorCode | Check |
|------|------|---------|------|----------------|-------|
| 0xA0 | 0x04 | | 0x69 | CommandSuccess | |

♦Failed:

Response packet:

| Head | Len | Address | Cmd | ErrorCode | Check | |
|-----------------------|-----------|-------------|------|-----------|-------|--|
| 0xA0 | 0x04 | | 0x69 | | | |
| | | | | | | |
| Parameter Description | ErrorCode | Error code. | | | | |

If this command succeeded, reader will be reset, and the profile configuration is stored in the internal flash.

2.1.21 cmd_get_rf_link_profile

Host packet:

| Head | Len | Address | Cmd | Check |
|------|------|---------|------|-------|
| 0xA0 | 0x03 | | 0x6A | |

♦Succeeded:

Response packet:

| Head | Len | Address | Cmd | ProfileID | Check | | | | | |
|-------------|-----------|---------|---|-----------|-------|--|--|--|--|--|
| 0xA0 | 0x04 | | 0x6A | | | | | | | |
| | | | | | | | | | | |
| | ProfileID | 0xD0 | Profile 0: Tari 25uS,FM0 40KHz. | | | | | | | |
| D . | | 0 D1 | Profile 1: Tari 25uS, Miller 4 250KHz. | | | | | | | |
| Parameter | | 0xD1 | Profile 1 is the recommended and default setting. | | | | | | | |
| Description | | 0xD2 | Profile 2: Tari 25uS,Miller 4 300KHz. | | | | | | | |
| | | 0xdD3 | Profile 3: Tari 6.25uS,FM0 400KHz. | | | | | | | |

♦Failed:

| Head | Len | Address | Cmd | ErrorCode | Check |
|--------------------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0x6A | | |
| | | | | | |
| Parameter Description | ErrorCode | | Err | or code. | |

2.1.22 cmd_get_rf_port_return_loss

Host packet:

| Head | Len | Address | Cmd | FreqParameter | Check | | | | |
|------------------|---------|---------|---|---------------|-------|--|--|--|--|
| 0xA0 | 0x04 | | 0x7E | | | | | | |
| | | | | | | | | | |
| Parameter | | | Please see the frequency parameter reference table. | | | | | | |
| 1 0.1 0.1110 001 | FreqPar | rameter | System will measure the return loss of current antenna port | | | | | | |
| Description | | | at the desired frequency. | | | | | | |

♦Succeeded:

Response packet:

| Head | Len | Address | Cmd | ReturnLoss | Check | | | | |
|-------------|-----------------|------------------------------------|---|------------|-------|--|--|--|--|
| 0xA0 | 0x04 | | 0x7E | | | | | | |
| | | | | | | | | | |
| Parameter | D. Annual I and | Return loss value, the unit is dB. | | | | | | | |
| Description | ReturnLoss | | $VSWR = (10^{RL/20} + 1)/(10^{RL/20} - 1).$ | | | | | | |

♦Failed:

| Head | Len | Address | Cmd | ErrorCode | Check |
|-----------------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0x7E | | |
| | | | | | |
| Parameter Description | ErrorCode | | Err | or code. | |

2.2 18000-6C Commands

2.2.1 cmd_inventory

Host packet:

| Head | Len | Address | Cmd | Repeat | Check | | | |
|--------------------------|--------|---------------------------------------|--|--|---|--|--|--|
| 0xA0 | 0x04 | | 0x80 | | | | | |
| | | | | | | | | |
| Parameter Description | Repeat | if the RF field onl only 30-50 mS, | 55, The inven y has one or this function | d. tory duration is minition two tags, the inventor provides a possibilitions on multi-ant dev | ry duration could be ty for fast antenna | | | |

When reader gets this command, the inventory for EPC GEN2 tags starts, tag data will be stored in the internal buffer.

Attention:

★When sets Repeat parameter to 255(0xFF), the anti-collision algorithm is optimized for applications with small tag quantity, which provide better efficiency and less response time.

♦Succeeded:

Response packet:

| Head | Len | Address | Cmd | AntID | TagCount | ReadRate | TotalRead | Check | | |
|---------|------|----------|-----------|---|--|----------------|-----------------|----------|--|--|
| 0xA0 | 0x0C | | 0x80 | | 2 Bytes | 2Bytes | 4Bytes | | | |
| | | | | | | | | | | |
| | | Ant | ID | | Ante | nna ID just us | sed. | | | |
| | | | | How many | tags have b | een identified | l. Tags are dif | fered by | | |
| | | TagCount | | EPC, Tags with the same EPC are considered as one. If | | | | | | |
| Param | atan | | | reader buffer is not cleared, tag count will be added up if | | | | | | |
| Descrip | | | | reader buffer is not cleared. | | | | | | |
| Descrip | шы | Daadl | D 1D / | | Tag identification speed (tag/second). Communications from | | | | | |
| | | | ReadRate | | the same tag are counted. | | | | | |
| | | Totali | Pand | Total tag identification count. Communications from the | | | | | | |
| | | | TotalRead | | same tag are counted. | | | | | |

♦Failed:

| Head | Len | Address | Cmd | ErrorCode | Check | | | |
|-----------------------|-----------|------------|------|-----------|-------|--|--|--|
| 0xA0 | 0x04 | | 0x80 | | | | | |
| | | | | | | | | |
| Parameter Description | ErrorCode | Error code | | | | | | |

2.2.2 cmd_read

Host packet:

| Head | Len | Address | Cmd | MemBank | WordAdd | WordCnt | Check | | |
|-------------|--------------------|------------|------------|---------|---|---|-------|--|--|
| 0xA0 | 0x06 | | 0x81 | | | | | | |
| | | | | | | | | | |
| | | | | | 0x00 | RESER | VED. | | |
| | | Men | nBank | | 0x01 | EPC. | | | |
| Parameter | | (Tag mer | nory ban | k) | 0X02 | TID. | | | |
| Description | | | | | 0X03 | USER. | | | |
| Description | W | ordAdd (Re | ad start a | ddress) | Please see the tag's spec for more information. | | | | |
| | | Wo | rdCnt | | Data length in WORD(16bits) unit. | | | | |
| | (Read data length) | | | | | Please see the tag's spec for more information. | | | |

♦Succeeded:

Response packet: This command may have multiple response packets, The quantity of response packets equals to the quantity of tags that response.

| Head | Len | Address | Cmd | TagCount | DataLen | Data | ReadLen | AntID | ReadCount | Check | |
|--------|--|---------|------|---|---|---------------|---------|-------|-----------|-------|--|
| 0xA0 | | | 0x81 | 2 Bytes | | N Bytes | | | | | |
| | | | | | | | | | | | |
| | | TagCo | ount | How many t | ags has beer | n read.16bits | • | | | | |
| | DataLen | | | | Length of useful data for a tag. (PC+CRC+EPC+ read data), unit is byte. | | | | | | |
| Param | atan | Dat | to | Useful data of the tag. | | | | | | | |
| Descri | | Dai | ia | PC (2 bytes) + EPC (bytes) + CRC (2 bytes) + read data. | | | | | | | |
| Descri | puon | Read | Len | Length of read data, unit is byte. | | | | | | | |
| | | Ant | ID | The high 6 bits are frequency parameter; the low 2 bits are antenna ID. | | | | | | | |
| | ReadCount How many times the tag has been successfully read. | | | | | | | | | | |

Attention:

★ If two tags have the same EPC, but different read data, then these two tags are considered different tags.

♦Failed:

| Head | Len | Address | Cmd | ErrorCode | Check |
|-----------------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0x81 | | |
| | | | | | |
| Parameter Description | ErrorCode | | En | ror code | |

2.2.3 cmd_write

Host packet:

| Head | Len | Address | Cmd | PassWord | MemBank | WordAdd | WordCnt | Data | Check |
|---------|------|--------------|-------------------------------|----------------|---------|---------------------------|---|-------------------|-----------|
| 0xA0 | | 0x82 4 Bytes | | | | WordCnt *2 | | | |
| | | _ | | | | | | | |
| | | | I | PassWord | | | Access passw | ord, 4 bytes. | |
| | | | | | | 0x | 00 | RESERV | /ED |
| | | | N | MenBank | | 0x01 | | EPC | |
| Param | atau | | (Tag 1 | memory bank |) | 0x | 02 | TID | |
| Descrip | | | | | | 0x03 | | USER | |
| Descrip | ouon | | 7 | Wand Add | | The unit is WORD(16bits). | | | |
| | | | WordAdd (Write start address) | | | | EPC area, no | otice that EPC st | arts from |
| | | | | | | | address 02, the first two 2 words are for PC+CRC. | | |
| | | W | ordCnt (| (Write data le | ngth) | The unit is WORD(16 bits) | | | |

♦Succeeded:

Response packet: This command may have multiple response packets; the quantity of response packets equals to the quantity of tags that response.

| Head | Len | Address | Cmd | TagCount | DataLen | Data | ErrCode | AntID | WriteCount | Check | | |
|---|-----------|---------|------|--|---------|---------|---------|-------|------------|-------|--|--|
| 0xA0 | | | 0x82 | 2 Bytes | | N Bytes | | | | | | |
| | | | | | | | | | | | | |
| | | TagCo | ount | How many tags have been written, 16 bits. | | | | | | | | |
| | | Datal | Len | Length of useful data of a tag. (PC+CRC+EPC) . The unit is byte. | | | | | | | | |
| Param | a a t a m | Dat | to | Useful data of the tag. | | | | | | | | |
| Descri | | Dai | а | PC(2 bytes) + EPC (bytes) + CRC (2bytes) | | | | | | | | |
| Descri | puon | ErrCo | ode | Operation result which is Error code. | | | | | | | | |
| AntID The high 6 bits are frequency parameter; the low 2 bits are antenna ID. | | | | | | | | | | | | |
| WriteCount How many times the tag has been written. | | | | | | | | | | | | |

♦Failed:

| Head | Len | Address | Cmd | ErrorCode | Check |
|--------------------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0x82 | | |
| | | | | | |
| Parameter Description | ErrorCode | | Err | ror code | |

2.2.4 cmd_lock

Host packet:

| Hest | Host packet. | | | | | | | | | |
|-------------|--------------|---------|--------------|-----------------|---------|------------------|----------|--|--|--|
| Head | Len | Address | Cmd | PassWord | Menbank | LockType | Check | | | |
| 0xA0 | 0x09 | | 0x83 | 4 Bytes | | | | | | |
| | | | | | | | | | | |
| | | P | Access | s password, 4 b | ytes. | | | | | |
| | | | | | 0x01 | User Mo | emory. | | | |
| | | N | Menbank | | 0x02 | TID Memory. | | | | |
| | | | nemory bank | -) | 0x03 | EPC Memory. | | | | |
| Parameter | | (Tug II | iemory outin | ·) | 0x04 | Access Password. | | | | |
| Description | | | | | 0x05 | Kill Password. | | | | |
| | | | | | 0x00 | Open. | | | | |
| | | L | ockType | | 0x01 | Lock. | | | | |
| | | (Lock o | peration typ | e) | 0x02 | Permanent open. | | | | |
| | | | | | 0x03 | Permane | nt lock. | | | |

♦Succeeded:

Response packet: This command may have multiple response packets, The quantity of response packets equals to the quantity of tags that response.

| Head | Len | Address | Cmd | TagCount | DataLen | Data | ErrCode | AntID | LockCount | Check | | | |
|--------|------|---------|---|---|---------------|-------------|---------|-------|-----------|-------|--|--|--|
| 0xA0 | | | 0x83 | 2 Bytes | | N Bytes | | | | | | | |
| | | | | | | | | | | | | | |
| | | TagCo | ount | How many t | ags have beer | locked.16 b | oits. | | | | | | |
| | | Datal | Len | Useful data for the tag (PC+CRC+EPC) .The unit is byte. | | | | | | | | | |
| Param | | Dat | ta | Useful data of the tag. | | | | | | | | | |
| Descri | | Dai | ıa | PC(2 bytes) + EPC (bytes) + CRC (2bytes) | | | | | | | | | |
| Descri | puon | ErrCo | ode | Operation result which is Error code. | | | | | | | | | |
| | | Antl | The high 6 bits are frequency parameter; the low 2 bits are antenna ID. | | | | | | | | | | |
| | | LockC | Count | How many times the tag has been locked. | | | | | | | | | |

♦Failed:

| Head | Len | Address | Cmd | ErrorCode | Check |
|-----------------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0x83 | | |
| | | | | | |
| Parameter Description | ErrorCode | | Er | ror code | |

2.2.5 cmd_kill

Host packet:

| Head | Len | Address | Cmd | PassWord | Check |
|-------------|------|---------|------|--------------|-------|
| 0xA0 | 0x07 | | 0x84 | 4 Bytes | |
| | | | | | |
| Parameter | D | -W/4 | | IZ:11 | .1 |
| Description | Pass | sWord | | Kill passwor | a |

♦Succeeded:

Response packet: This command may have multiple response packets, The quantity of response packets equals to the quantity of tags that response.

| Head | Len | Address | Cmd | TagCount | DataLen | Data | ErrCode | AntID | KillCount | Check | | | |
|---|------|---------|------|---|---------|------|------------------------------------|-------|-----------|-------|--|--|--|
| 0xA0 | | | 0x84 | 2 Bytes | | | | | | | | | |
| | | | | | | | | | | | | | |
| TagCount How many tags have been killed.16bits. | | | | | | | | | | | | | |
| DataLen Useful data for the tag (F | | | | | | | ag (PC+CRC+EPC) .The unit is byte. | | | | | | |
| Param | | Dat | ta | Useful data of the tag. | | | | | | | | | |
| Descri | | Da | ıa | PC(2 bytes) + EPC (bytes) + CRC (2bytes). | | | | | | | | | |
| Descri | puon | ErrC | ode | Operation result which is Error code. | | | | | | | | | |
| AntID The high 6 bits are frequency parameter; the low 2 bits are antenna ID. | | | | | | | | | | | | | |
| KillCount In this case, this byte only can be 1, because a tag only can be killed once. | | | | | | | | | | | | | |

♦Failed:

| Head | Len | Address | Cmd | ErrorCode | Check |
|-----------------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0x84 | | |
| | | | | | |
| Parameter Description | ErrorCode | | Err | or code. | |

2.2.6 cmd_set_access_epc_match

Host packet:

| Head | Len | Address | Cmd | Mode | EpcLen | Epc | Check | |
|-------------|-----|-----------------------|----------------------------|------|--------------------------|-----|-------|--|
| 0xA0 | | | 0x85 | | | | | |
| | | | | | | | | |
| | 7 | 3.6.1 | | 0 | Set EPC match effective. | | | |
| Parameter | 1 | Mode | 0x0 | | | | | |
| Description | Е | EpcLen Length of EPC. | | | | | | |
| | | Ерс | EPC, Length equals EpcLen. | | | | | |

Response packet:

| Head | Len | Address | Cmd | ErrorCode | Check |
|-------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0x85 | | |
| | | | | | |
| Parameter | ErrorCode | | E | or code. | |
| Description | Enorcode | | ЕП | or code. | |

2.2.7 cmd_get_access_epc_match

Host packet:

| Head | Len | Address | Cmd | Check |
|------|-----|---------|------|-------|
| 0xA0 | | | 0x86 | |
| | | | | |

| Head | Len | Address | Cmd | Status | EpcLen | EPC | Check | | | | |
|-------------|--------|--|------|--------|--------|-----------------------------|-------|--|--|--|--|
| 0xA0 | | | 0x86 | | | | | | | | |
| | | | | | | | | | | | |
| | Status | | 0x00 | | Е | EPC match is effective. | | | | | |
| | Status | | 0x01 | | EPG | EPC match is not effective. | | | | | |
| Parameter | EpcLen | The length of the EPC which EPC match is effective, if EPC match | | | | | | | | | |
| Description | Ерспен | is not effective, this byte doesn't return from reader. | | | | | | | | | |
| | EPC | The EPC which EPC match is effective, if EPC match is not | | | | | | | | | |
| | EPC | effective, this byte doesn't return from reader. | | | | | | | | | |

2.2.8 cmd_real_time_inventory

Host packet:

| Head | Len | Address | Cmd | Repeat | Check |
|--------------------------|--------|------------------------------------|---|---|---|
| 0xA0 | 0x04 | | 0x89 | | |
| | | | | | |
| Parameter Description | Repeat | When Rep is minim only ha duration | peat = 255 ized. For one or tron could be on provide switch ap | ntory round. 7, The inventory example, if the wo tags, the inventory only 30-50 m a possibility full plications on mercial evices. | RF field ventory S, this or fast |

When reader gets this command, the inventory for EPC GEN2 tags starts, tag data will **NOT** be stored in the internal buffer. The tag data is transferred in real time.

Attention:

★ The hardware has a dual CPU architecture, main CPU is responsible for tag inventory, and assistant CPU is responsible for data management. Inventory and data transfer are parallel and simultaneous. So the data transfer via serial port doesn't affect the efficiency of reader.

If there is(are) tag(s), reader responses below packets(multiple).

| Head | Len | Address | Cmd | FreqAnt | PC | EPC | RSSI | Check | | | |
|-------------------|-----|---------|------|---|---------|---------|------|-------|--|--|--|
| 0xA0 | | | 0x89 | | 2 bytes | N bytes | | | | | |
| | | | | | | | | | | | |
| | | FreqAnt | | The high 6 bits are frequency parameter; the low 2 bits are | | | | | | | |
| D (| | | | antenna ID. | | | | | | | |
| Paramet Descripti | | PC | C | Tag's PC. 2 bytes. | | | | | | | |
| Descripti | OII | EPC | | Tag's EPC. | | | | | | | |
| | | RSSI | | The RSSI when tag is identified. | | | | | | | |

After that, the command response is:

♦Succeeded:

Response packet:

| Head | Len | Addre ss | Cmd | AntID | ReadRate | TotalRead | Check | | | |
|-------------|-----------|--|---|------------|---------------|---------------|-------|--|--|--|
| | | 33 | | | | | | | | |
| 0xA0 | 0x0A | | 0x89 | | 2 bytes | 4 bytes | | | | |
| | | | | | | | | | | |
| | AntID | | The antenna ID of this inventory round. | | | | | | | |
| Parameter | ReadRate | | Ta | g ReadRate | of this comma | nd (tag/sec). | | | | |
| Description | T . ID 1 | Total tag identification count. Communications from the same tag are | | | | | | | | |
| | TotalRead | counted. | | | | | | | | |

♦Failed:

| Head | Len | Address | Cmd | ErrorCode | Check | | | | |
|-------------|-----------|------------------|------|-----------|-------|--|--|--|--|
| 0xA0 | 0x04 | | 0x89 | | | | | | |
| | | | | | | | | | |
| Parameter | ErrorCode | Code Error code. | | | | | | | |
| Description | Efforcode | | EH | or code. | | | | | |

2.2.9 cmd_fast_switch_ant_inventory

Host packet:

| Head | Len | Address | Cmd | A | Stay | В | Stay | C | Stay | D | Stay | Interval | Repeat | Check |
|------|----------|---------|------|---|---|-----------|----------|----------|------------|-------------|----------|---------------|---------|-------|
| 0xA0 | 0x0D | | 0x8A | | | | | | | | | | | |
| | | | | | | | | | | | | | | |
| | | First | work | ing ant | (00 - | - 03). If | set t | his byte | above 03 m | neans ignor | e it. | | | |
| | | Stay | | Inventory round for an antenna. Every antenna has this parameter. | | | | | | | | er. | | |
| | | В | | Second working ant $(00 - 03)$. If set this byte above 03 means ignore it. | | | | | | | ore it. | | | |
| | С | | | Third working ant $(00 - 03)$. If set this byte above 03 means ignore it. | | | | | | | re it. | | | |
| 参数说明 | D | | | Fourth working ant $(00-03)$. If set this byte above 03 means ignore it. | | | | | | | ore it. | | | |
| | Interval | | | | Rest time between switching antennas. During the cause of rest, RF output | | | | | | | | | |
| | | | | | will be cancelled, thus power consumption and heat generation are both | | | | | | | | | |
| | | | | | reduced. | | | | | | | | | |
| | | Repeat | | | | Re | peat the | inve | entory v | vith a | ibove ai | nt switch sec | quence. | |

When reader gets this command, the inventory for EPC GEN2 tags starts, tag data will **NOT** be stored in the internal buffer. The tag data is transferred in real time.

Meanwhile, the inventory duration is minimized in order to switch to the next antenna as soon as possible. If there's no tag, or only one or two tags in the RF field, the inventory duration on one antenna could be around 30mS. If there are more tags, the inventory duration on one antenna will increase. This command is an ideal solution for fast antenna switch applications on multi ant devices.

Attention:

- ★ The hardware has a dual CPU architecture, main CPU is responsible for tag inventory, and assistant CPU is responsible for data management. Inventory and data transfer are parallel and simultaneous. So the data transfer via serial port doesn't affect the efficiency of reader.
- ★In massive tag applications, please use cmd_real_time_inventory command which is more effective for large tag quantity applications.

If there is(are) tag(s), reader responses below packets(multiple).

| Head | Len | Address | Cmd | FreqAnt | PC | EPC | RSSI | Check | | | |
|-------------|-----|---------|------|---|---------|---------|------|-------|--|--|--|
| 0xA0 | | | 0x8A | | 2 bytes | N bytes | | | | | |
| | | | | | | | | | | | |
| | | FreqAnt | | The high 6 bits are frequency parameter; the low 2 bits are | | | | | | | |
| D | , | | | antenna ID. | | | | | | | |
| Parame | | PC | | Tag's PC. 2 bytes. | | | | | | | |
| Description | | EPC | | Tag's EPC. | | | | | | | |
| | | RSS | SI | The RSSI when tag is identified. | | | | | | | |

If the antenna detector is on, and antenna is not well connected, you might get below data package:

| Head | Len | Address | Cmd | AntID | ErrorCode | Check | | |
|-------------|-----------|---------|-----------------------------------|--------------|------------------|-------|--|--|
| 0xA0 | 0x05 | | 0x8A | | 0x22 | | | |
| | | | | | | | | |
| Parameter | AntID | | Unconnected antenna $ID(00-03)$. | | | | | |
| Description | ErrorCode | | 0x22, error | code for ant | enna is missing. | | | |

After that, the command response is:

♦Succeeded:

Response packet:

| Head | Len | Address | Cmd | TotalRead CommandDuration | | Check | | | |
|-------------|-----------------|-----------|---------|--|--|-------|--|--|--|
| 0xA0 | 0x0A | OA 0x8A | | 3 bytes | 4 bytes | | | | |
| | | | | | | | | | |
| | TotalRead | | | | How many tag data have been sent. an integer is stored | | | | |
| Parameter | | Totalicau | | in 3 bytes, high bits are aligned to the left. | | | | | |
| Description | Ca | a. dD | ıti a u | Command duration in millisecond, an integer is stored in | | | | | |
| | CommandDuration | | | 4 bytes, high bits are aligned to the left. | | | | | |

♦Failed:

| Head | Len | Address | Cmd | ErrorCode | Check | | | |
|-------------|-----------|-----------------------|------|-----------|-------|--|--|--|
| 0xA0 | 0x04 | | 0x8A | | | | | |
| | | | | | | | | |
| Parameter | FrrorCode | ErrorCode Error code. | | | | | | |
| Description | Efforcode | | | | | | | |

2.2.10 cmd_customized_session_target_inventory

Host packet:

| Head | Len | Address | Cmd | Session | Target | Repeat | Check | | |
|-----------------------|---------|---|------|---------|--------|--------|-------|--|--|
| 0xA0 | 0x06 | | 0x8B | | | | | | |
| | | | | | | | | | |
| D | Session | Desired session ID. | | | | | | | |
| Parameter Description | Target | Desired Inventoried Flag, $00 = A$, $01 = B$. | | | | | | | |
| Description | Repeat | Number of times of repeating this inventory. | | | | | | | |

When reader gets this command, the inventory for EPC GEN2 tags starts, tag data will **NOT** be stored in the internal buffer. The tag data is transferred in real time.

Attention:

★ The hardware has a dual CPU architecture, main CPU is responsible for tag inventory, and assistant CPU is responsible for data management. Inventory and data transfer are parallel and simultaneous. So the data transfer via serial port doesn't affect the efficiency of reader.

If there is(are) tag(s), reader responses below packets(multiple).

| Head | Len | Address | Cmd | FreqAnt | PC | EPC | RSSI | Check | |
|----------|------|---------|------|---|---------|---------|------|-------|--|
| 0xA0 | | | 0x8B | | 2 bytes | N bytes | | | |
| | | | | | | | | | |
| | Erag | Г. А. | | The high 6 bits are frequency parameter; the low 2 bits are | | | | | |
| D. | | FreqAnt | | antenna ID. | | | | | |
| Paramet | | Pe | С | Tag's PC. 2 bytes. | | | | | |
| Descript | 1011 | EF | PC C | Tag's EPC. | | | | | |
| | | RS | SI | The RSSI when tag is identified. | | | | | |

After that, the command response is:

♦Succeeded:

| Head | Len | Address | Cmd | AntID | ReadRate | TotalRead | Check | | |
|-------------|---|---------|---|--------------|-------------------|------------|-------|--|--|
| 0xA0 | 0x0A | | 0x8B | | 2bytes | 4 bytes | | | |
| | | | | | | | | | |
| D | AntID | | Th | e antenna Il | D of this invento | ory round. | | | |
| Parameter | ReadRate | | Tag ReadRate of this command (tag/sec). | | | | | | |
| Description | Description TotalRead Total tag identification count. Communications from the same tag are count. | | | | | | | | |

♦Failed:

| Head | Len | Address | Cmd | ErrorCode | Check |
|-----------------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0x8B | | |
| | | | | | |
| Parameter Description | ErrorCode | | Err | or code. | |

2.2.11 cmd_set_impinj_fast_tid

Host packet:

| Head | L | en | Add | ress | Cmd | Fas | stTID | Check | |
|-------------|-----------------------|-----|---------|------------------|------|-------|---------------|---------------|--|
| 0xA0 | 0x | k04 | | | 0x8C | | | | |
| | | | | | | | | | |
| Damamatan | | | | Any value except | | Class | Class EastTID | | |
| | Parameter Description | | FastTID | | 0x8D | | | Close FastTID | |
| Description | | | | | 0x8D | | | Open FastTID | |

Attention:

- **★**This function is only affective for some of Impinj Monza tag types.
- **★**This function improves the performance of identifying tag's TID.
- ★When this function takes effect, tag's TID will be included to tag's EPC, therefore, tag's EPC will be altered; the original data (PC + EPC) will be changed to altered PC + EPC + EPC's CRC + TID.
- ★If error occurred during identifying TID, only the original data (PC + EPC) will be sent.
- ★If you don't need this function, please turn it off, otherwise there will be unnecessary time consumption.
- ★This command doesn't store the status to internal flash. After reset or power on, the value stored in flash will be restored.

♦Succeeded:

Response packet:

| Head | Len | Address | Cmd | ErrorCode | Check |
|------|------|---------|------|----------------|-------|
| 0xA0 | 0x04 | | 0x8C | CommandSuccess | |

♦Failed:

| Head | Len | Address | Cmd | ErrorCode | Check |
|-----------------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0x8C | | |
| | | | | | |
| Parameter Description | ErrorCode | | Err | or code. | |

2.2.12 cmd_set_and_save_impinj_fast_tid

Please see_cmd_set_impinj_fast_tid command.

This command stores the configuration to internal flash. It won't be lost after power off.

2.2.13 cmd_get_impinj_fast_tid

Host packet:

| Head | Len | Address | Cmd | Check |
|------|------|---------|------|-------|
| 0xA0 | 0x03 | | 0x8E | |

| Head | Len | Address | Cmd | FastTID | Check | | | |
|-------------|---------|---------|------|---------------|-------|--|--|--|
| 0xA0 | 0x04 | | 0x8E | | | | | |
| | | | | | | | | |
| Parameter | EastTID | 0x8 | BD | Open FastTID | | | | |
| Description | FastTID | 0x0 | 00 | Close FastTID | | | | |

2.3 ISO 18000-6B Commands

2.3.1 cmd_iso18000_6b_inventory

Host packet:

| Head | Len | Address | Cmd | Check |
|------|------|---------|------|-------|
| 0xA0 | 0x03 | | 0xB0 | |

When reader gets this command, the inventory for EPC GEN2 tags starts, tag data will **NOT** be stored in the internal buffer. The tag data is transferred in real time.

If there is(are) tag(s), reader responses below packets(multiple).

| Head | Len | Address | Cmd | AntID | UID | Check | | | | |
|---------|-----------------|---------|------|---------------------------------|-------------|-------|--|--|--|--|
| 0xA0 | 0x0C | | 0xB0 | | 8 bytes | | | | | |
| | | | | | | | | | | |
| Parame | Parameter AntID | | | | Antenna ID. | | | | | |
| Descrip | Description UID | | | ISO 18000-6B tag UID (8 bytes). | | | | | | |

After that, the command response is:

♦Succeeded:

Response packet:

| Head | Len | Address | Cmd | AntID | TagFound | Check | |
|-------------|----------|---|----------|--------------|---------------|-------|--|
| 0xA0 | 0x05 | | 0xB0 | | | | |
| | | | | | | | |
| Parameter | AntID | The antenna ID of this inventory round. | | | | | |
| Description | TagFound | | How many | y unique tag | gs are found. | | |

♦Failed:

| Head | Len | Address | Cmd | ErrorCode | Check |
|-----------------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0xB0 | | |
| | | | | | |
| Parameter Description | ErrorCode | | En | ror code | |

2.3.2 cmd_iso18000_6b_read

Host packet:

| Head | Len | Address | Cmd | UID | StartAddress | Length | Check | | | | | | | |
|-------------|-------|---------|-------------------------|---------|-------------------|--------------------|-------|--|--|-------------------------|--|--|--|--|
| 0xA0 | 0x0D | | 0xB1 | 8 bytes | | | | | | | | | | |
| | | | | | | | | | | | | | | |
| D 4 | Ţ | ЛD | | The | UID of the tag wh | nich is being read | • | | | | | | | |
| Parameter | Start | Address | Start address for read. | | | | | | | Start address for read. | | | | |
| Description | Le | ngth | Read data length. | | | | | | | | | | | |

♦Succeeded:

Response packet:

| Head | Len | Address | Cmd | AntID | Data | Check | | |
|-------------|-------|--|------|-----------|---------|-------|--|--|
| 0xA0 | | | 0xB1 | | N bytes | | | |
| | | | | | | | | |
| Parameter | AntID | The antenna ID of this read operation. | | | | | | |
| Description | Data | | | Read data | | | | |

♦Failed:

| Head | Len | Address | Cmd | ErrorCode | Check |
|--------------------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0xB1 | | |
| | | | | | |
| Parameter Description | ErrorCode | | Err | or code. | |

2.3.3 cmd_iso18000_6b_write

Host packet:

| Head | Len | Address | Cmd | UID | StartAddress | Length | Data | Check | | | | |
|----------|-----|---------|--------|--|--------------|---------------|---------|--------------------|--|--|--|--|
| 0xA0 | | | 0xB2 | | | | N bytes | | | | | |
| | | | | | | | | | | | | |
| | | UI | D | The UID of the tag which is being written. | | | | | | | | |
| Paramet | ter | StartAc | ldress | | Star | t address for | write. | | | | | |
| Descript | ion | Len | gth | Write data length. | | | | Write data length. | | | | |
| | | Da | ta | Data to be written. | | | | | | | | |

♦Succeeded:

Response packet:

| Head | Len | Address | Cmd | AntID | WrittenCount | Check | | |
|-------------|--------------|---------|--|-------------|-----------------------|-------|--|--|
| 0xA0 | 0x05 | | 0xB2 | | | | | |
| | | | | | | | | |
| Parameter | AntID | | The antenna ID of this read operation. | | | | | |
| Description | WrittenCount | Hov | many b | ytes have b | een successfully writ | tten. | | |

Attention:

★ This command can write multiple bytes once. But when a byte is failed to write, the following bytes won't be written. Then the response packet returns the quantity of successfully written bytes.

♦Failed:

| Head | Len | Address | Cmd | ErrorCode | Check |
|--------------------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0xB2 | | |
| | | | | | |
| Parameter Description | ErrorCode | | Err | or code. | |

2.3.4 cmd_iso18000_6b_lock

Host packet:

| Head | Len | Address | Cmd | UID | LockAddress | Check | | | |
|-------------|-------|---|---------------------------|---------|-------------|-------|--|--|--|
| 0xA0 | 0x0C | | 0xB3 | 8 bytes | | | | | |
| | | | | | | | | | |
| Parameter | J | UID The UID of the tag which is being locked. | | | | | | | |
| Description | Lock. | Address | The address to be locked. | | | | | | |

♦Succeeded:

Response packet:

| Head | Len | Address | Cmd | AntID | Status | Check | | |
|-------------|-------|--|-----------------------------|-------|---------------------------|-------|--|--|
| 0xA0 | 0x05 | | 0xB3 | | | | | |
| | | | | | | | | |
| | AntID | The antenna ID of this read operation. | | | | | | |
| D | | | 000 | | The byte is successfully | | | |
| Parameter | | | 0x00 | | locked. | | | |
| Description | | | 0xFE The byte is already lo | | dy locked. | | | |
| | | | 0xFF | - | The byte can't be locked. | | | |

♦Failed:

| Head | Len | Address | Cmd | ErrorCode | Check |
|-----------------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0xB3 | | |
| | | | | | |
| Parameter Description | ErrorCode | | Err | or code. | |

2.3.5 cmd_iso18000_6b_query_lock

Host packet:

| Head | Len | Address | Cmd | UID | QueryAddress | Check | |
|-------------|-------|---------|---|---------|----------------------|-------|--|
| 0xA0 | 0x0C | | 0xB4 | 8 bytes | | | |
| | | | | | | | |
| Parameter | J | JID | The UID of the tag which is being locked. | | | | |
| Description | Query | Address | | The ad | dress to be queried. | | |

♦Succeeded:

Response packet:

| Head | Len | Address | Cmd | AntID | Status | Check |
|-------------|--------|--|-----------------------|-------|-----------------|---------|
| 0xA0 | 0x05 | | 0xB4 | | | |
| | | | | | | |
| D | AntID | The antenna ID of this read operation. | | | | • |
| Parameter | | 0x00 | | | The byte is not | locked. |
| Description | Status | | 0xFE The byte is lock | | ocked. | |

♦Failed:

| Head | Len | Address | Cmd | ErrorCode | Check |
|-----------------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0xB4 | | |
| | | | | | |
| Parameter Description | ErrorCode | | Err | or code. | |

2.4 Buffer Operation Commands

2.4.1 cmd_get_inventory_buffer

Host packet:

| Head | Len | Address | Cmd | Check |
|------|------|---------|------|-------|
| 0xA0 | 0x03 | | 0x90 | |

♦Succeeded:

Response packet: This command may have multiple response packets, the quantity of response packets equals to the quantity of tags that stored.

| Head | Len | Address | Cmd | TagCount | DataLen | Data | RSSI | FREQ | FreqAnt | InvCount | Check |
|--------|------------------|---------|------|--|--|-------------|------|------|---------|----------|-------|
| 0xA0 | | | 0x90 | 2 Bytes | | N bytes | | | | | |
| | | | | | | | | | | | |
| | TagCount DataLen | | | How many t | ags are store | ed. 16bits. | | | | | |
| | | | | Length of us | Length of useful data for a tag. (PC+CRC+EPC), unit is byte. | | | | | | |
| | | Data | 2 | Useful data of the tag. | | | | | | | |
| Paran | neter | Date | 1 | PC (2 bytes) + EPC (bytes) + CRC (2 bytes) | | | | | | | |
| Descri | iption | RSS | I | The RSSI of the tag that has been identified in the first time. | | | | | | | |
| | FreqAnt | | | The high 6 bits are frequency parameter; the low 2 bits are antenna ID. | | | | | | | |
| | | | | How many time the tag has been successfully identified. If the value is 0xFF, that means | | | | | | | |
| | InvCount | | | | the identification time is equal or greater than 255. | | | | | | |

Attention:

- **★**The data in the buffer won't be lost after execution of this command.
- **★**If the cmd_inventory is executed again, the tag data escalate in the buffer.
- ★Other 18000-6C commands can clear the buffer.

♦Failed:

| Head | Len | Address | Cmd | ErrorCode | Check |
|-------------|-----------|---------|------|-----------|-------|
| 0xA0 | 0x04 | | 0x90 | | |
| | | | | | |
| Parameter | E C - 4 - | | Г | 1- | |
| Description | ErrorCode | | En | ror code. | |

2.4.2 cmd_get_and_reset_inventory_buffer

Please see cmd_get_inventory_buffer command.

After execution of this command, the buffer is cleared.

2.4.3 cmd_get_inventory_buffer_tag_count

Host packet:

| Head | Len | Address | Cmd | Check |
|------|------|---------|------|-------|
| 0xA0 | 0x03 | | 0x92 | |

♦Succeeded:

Response packet:

| Head | Len | Address | Cmd | TagCount | Check |
|-----------------------|----------|---------|----------|-----------------|-------|
| 0xA0 | 0x05 | | 0x92 | 2 Bytes | |
| | | | | | |
| Parameter Description | TagCount | | How many | tags are stored | i. |

2.4.4 cmd_reset_inventory_buffer

Host packet:

| Head | Len | Address | Cmd | Check |
|------|------|---------|------|-------|
| 0xA0 | 0x03 | | 0x93 | |

| Head | Len | Address | Cmd | ErrorCode | Check |
|------|------|---------|------|----------------|-------|
| 0xA0 | 0x04 | | 0x93 | CommandSuccess | |

3 Error code

| 序号 | Code | Name | Description |
|----|------|---|------------------------------------|
| 1 | 0x10 | CommandSuccess | Command succeeded. |
| 2 | 0x11 | command_fail | Command failed. |
| 3 | 0x20 | mcu_reset_error | CPU reset error. |
| 4 | 0x21 | cw_on_error | Turn on CW error. |
| 5 | 0x22 | antenna_missing_error | Antenna is missing. |
| 6 | 0x23 | write_flash_error | Write flash error. |
| 7 | 0x24 | read_flash_error | Read flash error. |
| 8 | 0x25 | set_output_power_error | Set output power error. |
| 9 | 0x31 | tag_inventory_error | Error occurred when inventory. |
| 10 | 0x32 | tag_read_error | Error occurred when read. |
| 11 | 0x33 | tag_write_error | Error occurred when write. |
| 12 | 0x34 | tag_lock_error | Error occurred when lock. |
| 13 | 0x35 | tag_kill_error | Error occurred when kill. |
| 14 | 0x36 | no_tag_error | There is no tag to be operated. |
| 15 | 0x37 | inventory_ok_but_access_fail | Tag Inventoried but access failed. |
| 16 | 0x38 | buffer_is_empty_error | Buffer is empty. |
| 17 | 0x40 | access_or_password_error | Access failed or wrong password. |
| 18 | 0x41 | parameter_invalid | Invalid parameter. |
| 19 | 0x42 | parameter_invalid_wordCnt_too_long | WordCnt is too long. |
| 20 | 0x43 | parameter_invalid_membank_out_of_range | MemBank out of range. |
| 21 | 0x44 | parameter_invalid_lock_region_out_of_range | Lock region out of range. |
| 22 | 0x45 | parameter_invalid_lock_action_out_of_range | LockType out of range. |
| 23 | 0x46 | parameter_reader_address_invalid | Invalid reader address. |
| 24 | 0x47 | parameter_invalid_AntennaID_out_of_range | AntennaID out of range. |
| 25 | 0x48 | parameter_invalid_output_power_out_of_range | Output power out of range. |
| 26 | 0x49 | parameter_invalid_frequency_region_out_of_range | Frequency region out of range. |

YR8001 UHF RFID Serial Interface Protocol User's Guide V 2.38

| 27 | 0x4A | parameter_invalid_baudrate_out_of_range | Baud rate out of range. |
|----|------|---|---|
| 28 | 0x4B | parameter_beeper_mode_out_of_range | Buzzer behavior out of range. |
| 29 | 0x4C | parameter_epc_match_len_too_long | EPC match is too long. |
| 30 | 0x4D | parameter_epc_match_len_error | EPC match length wrong. |
| 31 | 0x4E | parameter_invalid_epc_match_mode | Invalid EPC match mode. |
| 32 | 0x4F | parameter_invalid_frequency_range | Invalid frequency range. |
| 33 | 0x50 | fail_to_get_RN16_from_tag | Failed to receive RN16 from tag. |
| 34 | 0x51 | parameter_invalid_drm_mode | Invalid DRM mode. |
| 35 | 0x52 | pll_lock_fail | PLL can not lock. |
| 36 | 0x53 | rf_chip_fail_to_response | No response from RF chip. |
| 37 | 0x54 | fail_to_achieve_desired_output_power | Can't achieve desired output power level. |
| 38 | 0x55 | copyright_authentication_fail | Can't authenticate firmware copyright. |
| 39 | 0x56 | spectrum_regulation_error | Spectrum regulation wrong. |
| 40 | 0x57 | output_power_too_low | Output power is too low. |

4 Frequency Parameter Reference Table

| Freq Para | Corresponding Frequency | Freq Para | Corresponding Frequency |
|-----------|-------------------------|-----------|-------------------------|
| 0(0x00) | 865.00 MHz | 30(0x1E) | 913.50 MHz |
| 1(0x01) | 865.50 MHz | 31(0x1F) | 914.00 MHz |
| 2(0x02) | 866.00 MHz | 32(0x20) | 914.50 MHz |
| 3(0x03) | 866.50 MHz | 33(0x21) | 915.00 MHz |
| 4(0x04) | 867.00 MHz | 34(0x22) | 915.50 MHz |
| 5(0x05) | 867.50 MHz | 35(0x23) | 916.00 MHz |
| 6(0x06) | 868.00 MHz | 36(0x24) | 916.50 MHz |
| 7(0x07) | 902.00 MHz | 37(0x25) | 917.00 MHz |
| 8(0x08) | 902.50 MHz | 38(0x26) | 917.50 MHz |
| 9(0x09) | 903.00 MHz | 39(0x27) | 918.00 MHz |
| 10(0x0A) | 903.50 MHz | 40(0x28) | 918.50 MHz |
| 11(0x0B) | 904.00 MHz | 41(0x29) | 919.00 MHz |
| 12(0x0C) | 904.50 MHz | 42(0x2A) | 919.50 MHz |
| 13(0x0D) | 905.00 MHz | 43(0x2B) | 920.00 MHz |
| 14(0x0E) | 905.50 MHz | 44(0x2C) | 920.50 MHz |
| 15(0x0F) | 906.00 MHz | 45(0x2D) | 921.00 MHz |
| 16(0x10) | 906.50 MHz | 46(0x2E) | 921.50 MHz |
| 17(0x11) | 907.00 MHz | 47(0x2F) | 922.00 MHz |
| 18(0x12) | 907.50 MHz | 48(0x30) | 922.50 MHz |
| 19(0x13) | 908.00 MHz | 49(0x31) | 923.00 MHz |
| 20(0x14) | 908.50 MHz | 50(0x32) | 923.50 MHz |
| 21(0x15) | 909.00 MHz | 51(0x33) | 924.00 MHz |
| 22(0x16) | 909.50 MHz | 52(0x34) | 924.50 MHz |
| 23(0x17) | 910.00 MHz | 53(0x35) | 925.00 MHz |
| 24(0x18) | 910.50 MHz | 54(0x36) | 925.50 MHz |
| 25(0x19) | 911.00 MHz | 55(0x37) | 926.00 MHz |
| 26(0x1A) | 911.50 MHz | 56(0x38) | 926.50 MHz |
| 27(0x1B) | 912.00 MHz | 57(0x39) | 927.00 MHz |
| 28(0x1C) | 912.50 MHz | 58(0x3A) | 927.50 MHz |
| 29(0x1D) | 913.00 MHz | 59(0x3B) | 928.00 MHz |

5 RSSI Parameter Reference Table

| RSSI Para | Corresponding Signal Strength | RSSI Para | Corresponding Signal Strength |
|-----------|-------------------------------|-----------|--------------------------------------|
| 98(0x62) | -31dBm | 64(0x40) | -66dBm |
| 97(0x61) | -32dBm | 63(0x3F) | -67dBm |
| 96(0x60) | -33dBm | 62(0x3E) | -68dBm |
| 95(0x5F) | -34dBm | 61(0x3D) | -69dBm |
| 94(0x5E) | -35dBm | 60(0x3C) | -70dBm |
| 93(0x5D) | -36dBm | 59(0x3B) | -71dBm |
| 92(0x5C) | -37dBm | 58(0x3A) | -72dBm |
| 91(0x5B) | -38dBm | 57(0x39) | -73dBm |
| 90(0x5A) | -39dBm | 56(0x38) | -74dBm |
| 89(0x59) | -41dBm | 55(0x37) | -75dBm |
| 88(0x58) | -42dBm | 54(0x36) | -76dBm |
| 87(0x57) | -43dBm | 53(0x35) | -77dBm |
| 86(0x56) | -44dBm | 52(0x34) | -78dBm |
| 85(0x55) | -45dBm | 51(0x33) | -79dBm |
| 84(0x54) | -46dBm | 50(0x32) | -80dBm |
| 83(0x53) | -47dBm | 49(0x31) | -81dBm |
| 82(0x52) | -48dBm | 48(0x30) | -82dBm |
| 81(0x51) | -49dBm | 47(0x2F) | -83dBm |
| 80(0x50) | -50dBm | 46(0x2E) | -84dBm |
| 79(0x4F) | -51dBm | 45(0x2D) | -85dBm |
| 78(0x4E) | -52dBm | 44(0x2C) | -86dBm |
| 77(0x4D) | -53dBm | 43(0x2B) | -87dBm |
| 76(0x4C) | -54dBm | 42(0x2A) | -88dBm |
| 75(0x4B) | -55dBm | 41(0x29) | -89dBm |
| 74(0x4A) | -56dBm | 40(0x28) | -90dBm |
| 73(0x49) | -57dBm | 39(0x27) | -91dBm |
| 72(0x48) | -58dBm | 38(0x26) | -92dBm |
| 71(0x47) | -59dBm | 37(0x25) | -93dBm |
| 70(0x46) | -60dBm | 36(0x24) | -94dBm |
| 69(0x45) | -61dBm | 35(0x23) | -95dBm |
| 68(0x44) | -62dBm | 34(0x22) | -96dBm |
| 67(0x43) | -63dBm | 33(0x21) | -97dBm |
| 66(0x42) | -64dBm | 32(0x20) | -98dBm |
| 65(0x41) | -55dBm | 31(0x1F) | -99dBm |

6 Checksum Function (Standard C Language)

```
unsigned char CheckSum(unsigned char *uBuff, unsigned char uBuffLen)
{
    unsigned char i,uSum=0;
    for(i=0;i<uBuffLen;i++)
    {
        uSum = uSum + uBuff[i];
    }
    uSum = (~uSum) + 1;
    return uSum;
}</pre>
```